

VOMS CC API

1.5.0

Generated by Doxygen 1.8.0

Fri May 25 2012 06:55:30

Contents

1	Data Structure Index	1
1.1	Data Structures	1
2	File Index	3
2.1	File List	3
3	Data Structure Documentation	5
3.1	attribute Struct Reference	5
3.1.1	Detailed Description	5
3.1.2	Field Documentation	5
3.1.2.1	name	5
3.1.2.2	qualifier	5
3.1.2.3	value	5
3.2	attributelist Struct Reference	6
3.2.1	Detailed Description	6
3.2.2	Field Documentation	6
3.2.2.1	attributes	6
3.2.2.2	grantor	6
3.3	contactdata Struct Reference	6
3.3.1	Detailed Description	6
3.3.2	Field Documentation	7
3.3.2.1	contact	7
3.3.2.2	host	7
3.3.2.3	nick	7
3.3.2.4	port	7
3.3.2.5	version	7
3.3.2.6	vo	7
3.4	data Struct Reference	7
3.4.1	Detailed Description	8
3.4.2	Field Documentation	8
3.4.2.1	cap	8
3.4.2.2	group	8

3.4.2.3	role	8
3.5	voms Struct Reference	8
3.5.1	Detailed Description	9
3.5.2	Constructor & Destructor Documentation	9
3.5.2.1	voms	9
3.5.2.2	voms	9
3.5.2.3	~voms	9
3.5.3	Member Function Documentation	9
3.5.3.1	GetAC	9
3.5.3.2	GetAttributes	9
3.5.3.3	GetTargets	9
3.5.3.4	operator=	9
3.5.4	Friends And Related Function Documentation	9
3.5.4.1	TranslateVOMS	9
3.5.4.2	vomsdata	9
3.5.5	Field Documentation	9
3.5.5.1	custom	9
3.5.5.2	date1	10
3.5.5.3	date2	10
3.5.5.4	fqan	10
3.5.5.5	serial	10
3.5.5.6	server	10
3.5.5.7	serverca	10
3.5.5.8	siglen	10
3.5.5.9	signature	10
3.5.5.10	std	10
3.5.5.11	type	11
3.5.5.12	uri	11
3.5.5.13	user	11
3.5.5.14	userca	11
3.5.5.15	version	11
3.5.5.16	voname	11
3.6	vomsdata Struct Reference	11
3.6.1	Detailed Description	12
3.6.2	Constructor & Destructor Documentation	12
3.6.2.1	vomsdata	12
3.6.2.2	~vomsdata	13
3.6.2.3	vomsdata	13
3.6.3	Member Function Documentation	13
3.6.3.1	AddTarget	13

3.6.3.2	Contact	13
3.6.3.3	Contact	13
3.6.3.4	ContactRaw	13
3.6.3.5	ContactRaw	14
3.6.3.6	ContactRESTRaw	14
3.6.3.7	DefaultData	14
3.6.3.8	ErrorMessage	14
3.6.3.9	Export	14
3.6.3.10	FindByAlias	14
3.6.3.11	FindByVO	15
3.6.3.12	Import	15
3.6.3.13	ListTargets	15
3.6.3.14	LoadCredentials	15
3.6.3.15	LoadSystemContacts	15
3.6.3.16	LoadUserContacts	16
3.6.3.17	Order	16
3.6.3.18	ResetOrder	16
3.6.3.19	ResetTargets	16
3.6.3.20	Retrieve	16
3.6.3.21	Retrieve	16
3.6.3.22	Retrieve	17
3.6.3.23	Retrieve	17
3.6.3.24	RetrieveFromCred	17
3.6.3.25	RetrieveFromCtx	17
3.6.3.26	RetrieveFromProxy	18
3.6.3.27	ServerErrors	18
3.6.3.28	SetLifetime	18
3.6.3.29	SetRetryCount	18
3.6.3.30	SetVerificationTime	18
3.6.3.31	SetVerificationType	18
3.6.4	Field Documentation	18
3.6.4.1	data	18
3.6.4.2	error	18
3.6.4.3	extra_data	19
3.6.4.4	workvo	19
4	File Documentation	21
4.1	voms_api.h File Reference	21
4.1.1	Define Documentation	22
4.1.1.1	NOGLOBUS	22

4.1.2	Typedef Documentation	22
4.1.2.1	check_sig	22
4.1.2.2	gss_cred_id_t	22
4.1.2.3	gss_ctx_id_t	22
4.1.3	Enumeration Type Documentation	22
4.1.3.1	data_type	22
4.1.3.2	recurse_type	23
4.1.3.3	verify_type	23
4.1.3.4	verror_type	23
4.1.4	Function Documentation	24
4.1.4.1	getVOMSMajorVersionNumber	24
4.1.4.2	getVOMSMinorVersionNumber	24
4.1.4.3	getVOMSPatchVersionNumber	24

Chapter 1

Data Structure Index

1.1 Data Structures

Here are the data structures with brief descriptions:

attribute	5
attributelist	6
contactdata	6
data	
User's characteristics: can be repeated. Generic name-value attribute : can be repeated	7
voms	8
vomsdata	11

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

voms_api.h	21
------------	-------	----

Chapter 3

Data Structure Documentation

3.1 attribute Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [name](#)
- std::string [qualifier](#)
- std::string [value](#)

3.1.1 Detailed Description

Definition at line 63 of file voms_api.h.

3.1.2 Field Documentation

3.1.2.1 std::string attribute::name

attribute's group

Definition at line 64 of file voms_api.h.

3.1.2.2 std::string attribute::qualifier

attribute's qualifier

Definition at line 65 of file voms_api.h.

3.1.2.3 std::string attribute::value

attribute's value

Definition at line 66 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.2 attributelist Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [grantor](#)
- std::vector<[attribute](#)> [attributes](#)

3.2.1 Detailed Description

Definition at line 69 of file voms_api.h.

3.2.2 Field Documentation

3.2.2.1 std::vector<[attribute](#)> [attributelist::attributes](#)

The attributes themselves.

Definition at line 71 of file voms_api.h.

3.2.2.2 std::string [attributelist::grantor](#)

Who granted these attributes.

Definition at line 70 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.3 contactdata Struct Reference

```
#include <voms_api.h>
```

Data Fields

- std::string [nick](#)
- std::string [host](#)
- std::string [contact](#)
- std::string [vo](#)
- int [port](#)
- int [version](#)

3.3.1 Detailed Description

Definition at line 83 of file voms_api.h.

3.3.2 Field Documentation

3.3.2.1 std::string contactdata::contact

The subject of the server's certificate

Definition at line 89 of file voms_api.h.

3.3.2.2 std::string contactdata::host

The hostname of the server

Definition at line 88 of file voms_api.h.

3.3.2.3 std::string contactdata::nick

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the FindBy* functions. The alias of the server

Definition at line 87 of file voms_api.h.

3.3.2.4 int contactdata::port

The port on which the server is listening

Definition at line 91 of file voms_api.h.

3.3.2.5 int contactdata::version

The version of globus under which the server is running

Definition at line 93 of file voms_api.h.

3.3.2.6 std::string contactdata::vo

The VO served by this server

Definition at line 90 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.4 data Struct Reference

User's characteristics: can be repeated. Generic name-value attribute : can be repeated.

```
#include <voms_api.h>
```

Data Fields

- std::string [group](#)
- std::string [role](#)
- std::string [cap](#)

3.4.1 Detailed Description

User's characteristics: can be repeated. Generic name-value attribute : can be repeated.

Definition at line 55 of file voms_api.h.

3.4.2 Field Documentation

3.4.2.1 std::string data::cap

user's capability

Definition at line 58 of file voms_api.h.

3.4.2.2 std::string data::group

user's group

Definition at line 56 of file voms_api.h.

3.4.2.3 std::string data::role

user's role

Definition at line 57 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.5 voms Struct Reference

```
#include <voms_api.h>
```

Public Member Functions

- [voms \(const voms &\)](#)
- [voms \(\)](#)
- [voms & operator= \(const voms &\)](#)
- [~voms \(\)](#)
- [AC * GetAC \(\)](#)
- [std::vector< attributelist > & GetAttributes \(\)](#)
- [std::vector< std::string > GetTargets \(\)](#)

Data Fields

- [int version](#)
- [int siglen](#)
- [std::string signature](#)
- [std::string user](#)
- [std::string userca](#)
- [std::string server](#)
- [std::string serverca](#)
- [std::string voname](#)

- std::string `uri`
- std::string `date1`
- std::string `date2`
- `data_type type`
- std::vector< `data` > `std`
- std::string `custom`
- std::vector< std::string > `fqan`
- std::string `serial`

Friends

- class `vomsdata`
- int `TranslateVOMS` (struct `vomsdata` *`vd`, std::vector< `voms` > &`v`, int *`error`)

3.5.1 Detailed Description

Definition at line 98 of file `voms_api.h`.

3.5.2 Constructor & Destructor Documentation

3.5.2.1 `voms::voms(const voms &)`

3.5.2.2 `voms::voms()`

3.5.2.3 `voms::~voms()`

3.5.3 Member Function Documentation

3.5.3.1 `AC* voms::GetAC()`

3.5.3.2 `std::vector<attributelist>& voms::GetAttributes()`

Generic attributes

3.5.3.3 `std::vector<std::string> voms::GetTargets()`

3.5.3.4 `voms& voms::operator=(const voms &)`

3.5.4 Friends And Related Function Documentation

3.5.4.1 `int TranslateVOMS(struct vomsdata * vd, std::vector< voms > & v, int * error) [friend]`

3.5.4.2 `friend class vomsdata [friend]`

Definition at line 99 of file `voms_api.h`.

3.5.5 Field Documentation

3.5.5.1 `std::string voms::custom`

The data returned by an S command

Definition at line 113 of file `voms_api.h`.

3.5.5.2 std::string voms::date1

Beginning of validity of the user info

Definition at line 109 of file voms_api.h.

3.5.5.3 std::string voms::date2

End of validity of the user info

Definition at line 110 of file voms_api.h.

3.5.5.4 std::vector<std::string> voms::fqan

Keeps the data in the compact format

Definition at line 115 of file voms_api.h.

3.5.5.5 std::string voms::serial

Serial number. "0" if coming from non-ac

Definition at line 116 of file voms_api.h.

3.5.5.6 std::string voms::server

The VOMS server DN, as from its certificate

Definition at line 105 of file voms_api.h.

3.5.5.7 std::string voms::serverca

The CA which signed the VOMS certificate

Definition at line 106 of file voms_api.h.

3.5.5.8 int voms::siglen

The length of the VOMS server signature

Definition at line 101 of file voms_api.h.

3.5.5.9 std::string voms::signature

The VOMS server signature

Definition at line 102 of file voms_api.h.

3.5.5.10 std::vector<data> voms::std

User's characteristics

Definition at line 112 of file voms_api.h.

3.5.5.11 `data_type voms::type`

The type of data returned

Definition at line 111 of file voms_api.h.

3.5.5.12 `std::string voms::uri`

The URI of the VOMS server

Definition at line 108 of file voms_api.h.

3.5.5.13 `std::string voms::user`

The user's DN, as from his certificate

Definition at line 103 of file voms_api.h.

3.5.5.14 `std::string voms::userca`

The CA which signed the user's certificate

Definition at line 104 of file voms_api.h.

3.5.5.15 `int voms::version`

0 means data didn't originate from an AC

Definition at line 100 of file voms_api.h.

3.5.5.16 `std::string voms::vuname`

The name of the VO to which the VOMS belongs

Definition at line 107 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

3.6 vomsdata Struct Reference

```
#include <voms_api.h>
```

Data Structures

- class **Initializer**

Public Member Functions

- [vomsdata \(std::string voms_dir="", std::string cert_dir ""\)](#)
- bool [LoadSystemContacts \(std::string dir ""\)](#)
- bool [LoadUserContacts \(std::string dir ""\)](#)
- std::vector< [contactdata](#) > [FindByAlias \(std::string alias\)](#)

- std::vector< [contactdata](#) > [FindByVO](#) (std::string vo)
- void [Order](#) (std::string att)
- void [ResetOrder](#) (void)
- void [AddTarget](#) (std::string target)
- std::vector< std::string > [ListTargets](#) (void)
- void [ResetTargets](#) (void)
- std::string [ServerErrors](#) (void)
- bool [Retrieve](#) (X509 *cert, STACK_OF(X509)*chain, [recurse_type](#) how=[RECURSE_CHAIN](#))
- bool [Contact](#) (std::string hostname, int port, std::string servsubject, std::string command)
- bool [Contact](#) (std::string hostname, int port, std::string servsubject, std::string command, int timeout)
- bool [ContactRaw](#) (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version)
- bool [ContactRaw](#) (std::string hostname, int port, std::string servsubject, std::string command, std::string &raw, int &version, int timeout)
- void [SetVerificationType](#) ([verify_type](#) how)
- void [SetLifetime](#) (int lifetime)
- bool [Import](#) (std::string buffer)
- bool [Export](#) (std::string &data)
- bool [DefaultData](#) ([voms](#) &)
- std::string [ErrorMessage](#) (void)
- bool [RetrieveFromCtx](#) (gss_ctx_id_t context, [recurse_type](#) how)
- bool [RetrieveFromCred](#) (gss_cred_id_t credential, [recurse_type](#) how)
- bool [Retrieve](#) (X509_EXTENSION *ext)
- bool [RetrieveFromProxy](#) ([recurse_type](#) how)
- bool [Retrieve](#) (FILE *file, [recurse_type](#) how)
- bool [Retrieve](#) (AC *ac)
- [~vomsdata](#) ()
- [vomsdata](#) (const [vomsdata](#) &)
- void [SetRetryCount](#) (int retryCount)
- void [SetVerificationTime](#) (time_t)
- bool [LoadCredentials](#) (X509 *, EVP_PKEY *, STACK_OF(X509)*)
- bool [ContactRESTRaw](#) (const std::string &, int, const std::string &, std::string &, int, int)

Data Fields

- [verror_type](#) error
- std::vector< [voms](#) > data
- std::string workvo
- std::string extra_data

3.6.1 Detailed Description

Definition at line 194 of file voms_api.h.

3.6.2 Constructor & Destructor Documentation

3.6.2.1 [vomsdata::vomsdata](#) (std::string [voms_dir](#) = " ", std::string [cert_dir](#) = " ")

Parameters

voms_dir	The directory which contains the certificate of the VOMS server
cert_dir	The directory which contains the certificate of the CA

If [voms_dir](#) is empty, the value of the environment variable X509_VOMS_DIR is taken.

If cert_dir is empty, the value of the environment variable X509_CERT_DIR is taken.

3.6.2.2 `vomsdata::~vomsdata()`

3.6.2.3 `vomsdata::vomsdata(const vomsdata &)`

3.6.3 Member Function Documentation

3.6.3.1 `void vomsdata::AddTarget(std::string target)`

Adds a target to the AC.

```
\param target The target to be added. it should be a FQDN.
```

3.6.3.2 `bool vomsdata::Contact(std::string hostname, int port, std::string servsubject, std::string command)`

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the --include functionality.
\param hostname FQDN of the VOMS server
\param port the port on which the VOMS server is listening
\param servsubject the subject of the server's certificate
\param command the command sent to the server
\return failure (F) or success (T)

3.6.3.3 `bool vomsdata::Contact(std::string hostname, int port, std::string servsubject, std::string command, int timeout)`

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the --include functionality.
\param hostname FQDN of the VOMS server
\param port the port on which the VOMS server is listening
\param servsubject the subject of the server's certificate
\param command the command sent to the server
\return failure (F) or success (T)

3.6.3.4 `bool vomsdata::ContactRaw(std::string hostname, int port, std::string servsubject, std::string command, std::string & raw, int & version)`

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

Parameters

<code>hostname</code>	FQDN of the VOMS server
<code>port</code>	the port on which the VOMS server is listening
<code>servsubject</code>	the subject of the server's certificate
<code>command</code>	the command sent to the server
<code>raw</code>	OUTPUT PARAMETER the answer from the server
<code>version</code>	OUTPUT PARAMETER the version of the answer

Returns

failure (F) or success (T)

3.6.3.5 bool vomsdata::ContactRaw (std::string *hostname*, int *port*, std::string *servsubject*, std::string *command*, std::string & *raw*, int & *version*, int *timeout*)

Same as Contact, however it does not start the verification process, and the message received from the server is not parsed.

Parameters

<i>hostname</i>	FQDN of the VOMS server
<i>port</i>	the port on which the VOMS server is listening
<i>servsubject</i>	the subject of the server's certificate
<i>command</i>	the command sent to the server
<i>raw</i>	OUTPUT PARAMETER the answer from the server
<i>version</i>	OUTPUT PARAMETER the version of the answer

Returns

failure (F) or success (T)

3.6.3.6 bool vomsdata::ContactRESTRaw (const std::string &, int , const std::string &, std::string &, int , int)

3.6.3.7 bool vomsdata::DefaultData (voms &)

Get the default data extension from those present in the pseudo certificate

3.6.3.8 std::string vomsdata::ErrorMessage (void)

Gets a textual description of the error.

Returns

A string containing the error message.

3.6.3.9 bool vomsdata::Export (std::string & *data*)

Exports data from [vomsdata::data](#) to the format used for inclusion into a certificate.

The function doesn't verify the data

Parameters

<i>data</i>	The certificate extension
-------------	---------------------------

Returns

Failure (F) or Success (T)

3.6.3.10 std::vector<[contactdata](#)> vomsdata::FindByAlias (std::string *alias*)

Finds servers which share a common alias.

Parameters

<i>alias</i>	The alias to look for.
--------------	------------------------

Returns

The servers found. The order in which they are returned is unspecified.

3.6.3.11 std::vector<contactdata> vomsdata::FindByVO (std::string *vo*)

Finds servers which serve a common VO

Parameters

<i>vo</i>	The VO name to look for.
-----------	--------------------------

Returns

The servers found. The order in which they are returned is unspecified.

3.6.3.12 bool vomsdata::Import (std::string *buffer*)

Converts data from the format used for inclusion into a certificate to the internal format

The function does verify the data.

Parameters

<i>buffer</i>	contains the data to be converted
---------------	-----------------------------------

Returns

Failure (F) or Success (T)

3.6.3.13 std::vector<std::string> vomsdata::ListTargets (void)

Returns the list of targets.

3.6.3.14 bool vomsdata::LoadCredentials (X509 * , EVP_PKEY * , STACK_OF(X509)*)**3.6.3.15 bool vomsdata::LoadSystemContacts (std::string *dir* = "")**

Loads the system wide configuration files.

Parameters

<i>dir</i>	The directory in which the files are stored.
------------	--

If *dir* is empty, defaults to /opt/edg/etc/vomses.

Returns

True if all went OK, false otherwise.

3.6.3.16 bool vomsdata::LoadUserContacts (std::string *dir* = " ")

Loads the user-specific configuration files.

Parameters

<i>dir</i>	The directory in which the files are stored.
------------	--

If *dir* is empty, defaults to \$VOMS_USERCONF. If this is empty too, defaults to \$HOME/.edg/vomses, or to *~/.edg/vomses* as a last resort.

Returns

True if all went OK, false otherwise.

3.6.3.17 void vomsdata::Order (std::string *att*)

Sets up the ordering of the results.

Defines the ordering of the data returned by Contact(). Results are ordered in the same order as the calls to this function.
\param *att* The attribute to be ordered.

3.6.3.18 void vomsdata::ResetOrder (void)

Resets the ordering.

3.6.3.19 void vomsdata::ResetTargets (void)

Resets the target list.

3.6.3.20 bool vomsdata::Retrieve (X509 * *cert*, STACK_OF(X509)* *chain*, recurse_type *how*=RECURSE_CHAIN)

Extracts the VOMS extension from an X.509 certificate. The function doesn't check the validity of the certificates, but it does check the content of the user data.

Parameters

<i>cert</i>	The certificate with the VOMS extensions
<i>chain</i>	The chain of the validation certificates (only the intermediate ones)
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

3.6.3.21 bool vomsdata::Retrieve (X509_EXTENSION * *ext*)

Gets VOMS information from the given extension

Parameters

<i>ext</i>	The extension to parse.
------------	-------------------------

Returns

failure (F) or success (T)

3.6.3.22 bool vomsdata::Retrieve (FILE * *file*, recurse_type *how*)

Gets VOMS information from a proxy saved as a file.

Parameters

<i>file</i>	the file name
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

Note: Does NOT verify that the proxy is valid. Such verification must be obtained through other means.

3.6.3.23 bool vomsdata::Retrieve (AC * *ac*)

Gets VOMS information from the AC

Parameters

<i>ext</i>	The extension to parse.
------------	-------------------------

Returns

failure (F) or success (T)

3.6.3.24 bool vomsdata::RetrieveFromCred (gss_cred_id_t *credential*, recurse_type *how*)

Gets VOMS information from the given globus credential

Parameters

<i>credential</i>	The credential from which to retrieve the certificate.
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

3.6.3.25 bool vomsdata::RetrieveFromCtx (gss_ctx_id_t *context*, recurse_type *how*)

Gets VOMS information from the given globus context

Parameters

<i>context</i>	The context from which to retrieve the certificate.
<i>how</i>	Recursion type

Returns

failure (F) or success (T)

3.6.3.26 bool vomsdata::RetrieveFromProxy (recurse_type *how*)

Gets VOMS information from an existing globus proxy

Parameters

<i>how</i>	Recursion type
------------	----------------

Returns

failure (F) or success (T)

3.6.3.27 std::string vomsdata::ServerErrors (void)

Gets the error message returned by the server

3.6.3.28 void vomsdata::SetLifetime (int *lifetime*)

Set requested lifetime for the [Contact\(\)](#) call.

Parameters

<i>lifetime</i>	Requested lifetime, in seconds
-----------------	--------------------------------

3.6.3.29 void vomsdata::SetRetryCount (int *retryCount*)**3.6.3.30 void vomsdata::SetVerificationTime (time_t)****3.6.3.31 void vomsdata::SetVerificationType (verify_type *how*)**

Sets the type of verification done on the data.

Parameters

<i>how</i>	The type of verification.
------------	---------------------------

3.6.4 Field Documentation**3.6.4.1 std::vector<voms> vomsdata::data**

User's info, as in the certificate extension. It may contain data gathered from more than one VOMS server,
Definition at line 368 of file voms_api.h.

3.6.4.2 verror_type vomsdata::error

Error code

Definition at line 213 of file voms_api.h.

3.6.4.3 std::string vomsdata::extra_data

The data specified by the user with the --include switch.

Note that this field doesn't contain the result of a request to the VOMS server, but instead data specified by the user.

The reason for the introduction of this extension is to let a user include important data into his proxy certificate, like, for example, a kerberos ticket

Definition at line 372 of file voms_api.h.

3.6.4.4 std::string vomsdata::workvo

The value of the -vo option of the voms-proxy-init command

Definition at line 371 of file voms_api.h.

The documentation for this struct was generated from the following file:

- [voms_api.h](#)

Chapter 4

File Documentation

4.1 voms_api.h File Reference

```
#include <fstream>
#include <string>
#include <vector>
#include <openssl/x509.h>
#include <openssl/bio.h>
#include <sys/types.h>
#include "newformat.h"
```

Data Structures

- struct `data`
User's characteristics: can be repeated. Generic name-value attribute : can be repeated.
- struct `attribute`
- struct `attributelist`
- struct `contactdata`
- struct `voms`
- struct `vomsdata`
- class `vomsdata::Initializer`

Defines

- #define `NOGLOBUS`

TypeDefs

- typedef void * `gss_cred_id_t`
- typedef void * `gss_ctx_id_t`
- typedef bool(* `check_sig`)(X509 *, void *, `verror_type` &)

Enumerations

- enum `data_type` { `TYPE_NODATA`, `TYPE_STD`, `TYPE_CUSTOM` }
The type of data returned.
- enum `recurse_type` { `RECURSE_CHAIN`, `RECURSE_NONE`, `RECURSE_DEEP` }

- enum `verify_type` {
 `VERIFY_FULL` = 0xffffffff, `VERIFY_NONE` = 0x00000000, `VERIFY_DATE` = 0x00000001, `VERIFY_TARGET` = 0x00000002,
`VERIFY_KEY` = 0x00000004, `VERIFY_SIGN` = 0x00000008, `VERIFY_ORDER` = 0x00000010, `VERIFY_ID` = 0x00000020,
`VERIFY_CERTLIST` = 0x00000040 }
- enum `verror_type` {
 `VERR_NONE`, `VERR_NOSOCKET`, `VERR_NOIDENT`, `VERR_COMM`,
`VERR_PARAM`, `VERR_NOEXT`, `VERR_NOINIT`, `VERR_TIME`,
`VERR_IDCHECK`, `VERR_EXTRAINFO`, `VERR_FORMAT`, `VERR_NODATA`,
`VERR_PARSE`, `VERR_DIR`, `VERR_SIGN`, `VERR_SERVER`,
`VERR_MEM`, `VERR_VERIFY`, `VERR_TYPE`, `VERR_ORDER`,
`VERR_SERVERCODE`, `VERR_NOTAVAIL`, `VERR_FILE` }

Error codes.

Functions

- int `getVOMSMajorVersionNumber` (void)
- int `getVOMSMinorVersionNumber` (void)
- int `getVOMSPatchVersionNumber` (void)

4.1.1 Define Documentation

4.1.1.1 #define NOGLOBUS

Definition at line 33 of file voms_api.h.

4.1.2 Typedef Documentation

4.1.2.1 `typedef bool(* check_sig)(X509 *, void *, verror_type &)`

Definition at line 190 of file voms_api.h.

4.1.2.2 `typedef void* gss_cred_id_t`

Definition at line 42 of file voms_api.h.

4.1.2.3 `typedef void* gss_ctx_id_t`

Definition at line 43 of file voms_api.h.

4.1.3 Enumeration Type Documentation

4.1.3.1 `enum data_type`

The type of data returned.

Enumerator:

- `TYPE_NODATA`** no data
- `TYPE_STD`** group, role, capability triplet
- `TYPE_CUSTOM`** result of an S command

Definition at line 77 of file voms_api.h.

4.1.3.2 enum recurse_type

Enumerator:

RECURSE_CHAIN
RECURSE_NONE
RECURSE_DEEP

Definition at line 143 of file voms_api.h.

4.1.3.3 enum verify_type

Enumerator:

VERIFY_FULL
VERIFY_NONE
VERIFY_DATE
VERIFY_TARGET
VERIFY_KEY
VERIFY_SIGN
VERIFY_ORDER
VERIFY_ID
VERIFY_CERTLIST

Definition at line 149 of file voms_api.h.

4.1.3.4 enum verror_type

Error codes.

Enumerator:

VERR_NONE
VERR_NOSOCKET Socket problem
VERR_NOIDENT Cannot identify itself (certificate problem)
VERR_COMM Server problem
VERR_PARAM Wrong parameters
VERR_NOEXT VOMS extension missing
VERR_NOINIT Initialization error
VERR_TIME Error in time checking
VERR_IDCHECK User data in extension different from the real ones
VERR_EXTRAINFO VO name and URI missing
VERR_FORMAT Wrong data format
VERR_NODATA Empty extension
VERR_PARSE Parse error
VERR_DIR Directory error
VERR_SIGN Signature error
VERR_SERVER Unidentifiable VOMS server
VERR_MEM Memory problems
VERR_VERIFY Generic verification error

VERR_TYPE Returned data of unknown type

VERR_ORDER Ordering different than required

VERR_SERVERCODE Error message from the server

VERR_NOTAVAIL Method not available

VERR_FILE Error reading data from file

Definition at line 163 of file voms_api.h.

4.1.4 Function Documentation

4.1.4.1 `int getVOMSMajorVersionNumber(void)`

4.1.4.2 `int getVOMSMinorVersionNumber(void)`

4.1.4.3 `int getVOMSPatchVersionNumber(void)`

Index

~voms
 voms, 9
~vomsdata
 vomsdata, 13

AddTarget
 vomsdata, 13

attribute, 5
 name, 5
 qualifier, 5
 value, 5

attributelist, 6
 attributes, 6
 grantor, 6

attributes
 attributelist, 6

cap
 data, 8

check_sig
 voms_api.h, 22

Contact
 vomsdata, 13

contact
 contactdata, 7

ContactRETRaw
 vomsdata, 14

ContactRaw
 vomsdata, 13, 14

contactdata, 6
 contact, 7
 host, 7
 nick, 7
 port, 7
 version, 7
 vo, 7

custom
 voms, 9

data, 7
 cap, 8
 group, 8
 role, 8
 vomsdata, 18

data_type
 voms_api.h, 22

date1
 voms, 9

date2
 voms, 10

DefaultData
 vomsdata, 14

error
 vomsdata, 18

ErrorMessage
 vomsdata, 14

Export
 vomsdata, 14

extra_data
 vomsdata, 18

FindByAlias
 vomsdata, 14

FindByVO
 vomsdata, 15

fqan
 voms, 10

GetAC
 voms, 9

GetAttributes
 voms, 9

GetTargets
 voms, 9

getVOMSMajorVersionNumber
 voms_api.h, 24

getVOMSMinorVersionNumber
 voms_api.h, 24

getVOMSPatchVersionNumber
 voms_api.h, 24

grantor
 attributelist, 6

group
 data, 8

gss_cred_id_t
 voms_api.h, 22

gss_ctx_id_t
 voms_api.h, 22

host
 contactdata, 7

Import
 vomsdata, 15

ListTargets
 vomsdata, 15

LoadCredentials
 vomsdata, 15

LoadSystemContacts

vomsdata, 15
 LoadUserContacts
 vomsdata, 15

 NOGLOBUS
 voms_api.h, 22
 name
 attribute, 5
 nick
 contactdata, 7

 operator=
 voms, 9
 Order
 vomsdata, 16

 port
 contactdata, 7

 qualifier
 attribute, 5

 RECURSE_CHAIN
 voms_api.h, 23
 RECURSE_DEEP
 voms_api.h, 23
 RECURSE_NONE
 voms_api.h, 23
 recurse_type
 voms_api.h, 22
 ResetOrder
 vomsdata, 16
 ResetTargets
 vomsdata, 16
 Retrieve
 vomsdata, 16, 17
 RetrieveFromCred
 vomsdata, 17
 RetrieveFromCtx
 vomsdata, 17
 RetrieveFromProxy
 vomsdata, 18
 role
 data, 8

 serial
 voms, 10
 server
 voms, 10
 ServerErrors
 vomsdata, 18
 serverca
 voms, 10
 SetLifetime
 vomsdata, 18
 SetRetryCount
 vomsdata, 18
 SetVerificationTime
 vomsdata, 18
 SetVerificationType
 vomsdata, 18

 siglen
 voms, 10
 signature
 voms, 10
 std
 voms, 10

 TYPE_CUSTOM
 voms_api.h, 22
 TYPE_NODATA
 voms_api.h, 22
 TYPE_STD
 voms_api.h, 22
 TranslateVOMS
 voms, 9
 type
 voms, 10

 uri
 voms, 11
 user
 voms, 11
 userca
 voms, 11

 VERIFY_CERTLIST
 voms_api.h, 23
 VERIFY_DATE
 voms_api.h, 23
 VERIFY_FULL
 voms_api.h, 23
 VERIFY_ID
 voms_api.h, 23
 VERIFY_KEY
 voms_api.h, 23
 VERIFY_NONE
 voms_api.h, 23
 VERIFY_ORDER
 voms_api.h, 23
 VERIFY_SIGN
 voms_api.h, 23
 VERIFY_TARGET
 voms_api.h, 23
 VERR_COMM
 voms_api.h, 23
 VERR_DIR
 voms_api.h, 23
 VERR_EXTRAINFO
 voms_api.h, 23
 VERR_FILE
 voms_api.h, 24
 VERR_FORMAT
 voms_api.h, 23
 VERR_IDCHECK
 voms_api.h, 23
 VERR_MEM
 voms_api.h, 23
 VERR_NODATA

voms_api.h, 23
VERR_NOEXT
 voms_api.h, 23
VERR_NOIDENT
 voms_api.h, 23
VERR_NOINIT
 voms_api.h, 23
VERR_NONE
 voms_api.h, 23
VERR_NOSOCKET
 voms_api.h, 23
VERR_NOTAVAIL
 voms_api.h, 24
VERR_ORDER
 voms_api.h, 24
VERR_PARAM
 voms_api.h, 23
VERR_PARSE
 voms_api.h, 23
VERR_SERVER
 voms_api.h, 23
VERR_SERVERCODE
 voms_api.h, 24
VERR_SIGN
 voms_api.h, 23
VERR_TIME
 voms_api.h, 23
VERR_TYPE
 voms_api.h, 23
VERR_VERIFY
 voms_api.h, 23
value
 attribute, 5
verify_type
 voms_api.h, 23
verror_type
 voms_api.h, 23
version
 contactdata, 7
 voms, 11
vo
 contactdata, 7
voms, 8
 ~voms, 9
 custom, 9
 date1, 9
 date2, 10
 fqn, 10
 GetAC, 9
 GetAttributes, 9
 GetTargets, 9
 operator=, 9
 serial, 10
 server, 10
 serverca, 10
 siglen, 10
 signature, 10
 std, 10
TranslateVOMS, 9
type, 10
uri, 11
user, 11
userca, 11
version, 11
voms, 9
vomsdata, 9
voname, 11
voms_api.h
 RECURSE_CHAIN, 23
 RECURSE_DEEP, 23
 RECURSE_NONE, 23
 TYPE_CUSTOM, 22
 TYPE_NODATA, 22
 TYPE_STD, 22
 VERIFY_CERTLIST, 23
 VERIFY_DATE, 23
 VERIFY_FULL, 23
 VERIFY_ID, 23
 VERIFY_KEY, 23
 VERIFY_NONE, 23
 VERIFY_ORDER, 23
 VERIFY_SIGN, 23
 VERIFY_TARGET, 23
 VERR_COMM, 23
 VERR_DIR, 23
 VERR_EXTRAINFO, 23
 VERR_FILE, 24
 VERR_FORMAT, 23
 VERR_IDCHECK, 23
 VERR_MEM, 23
 VERR_NODATA, 23
 VERR_NOEXT, 23
 VERR_NOIDENT, 23
 VERR_NOINIT, 23
 VERR_NONE, 23
 VERR_NOSOCKET, 23
 VERR_NOTAVAIL, 24
 VERR_ORDER, 24
 VERR_PARAM, 23
 VERR_PARSE, 23
 VERR_SERVER, 23
 VERR_SERVERCODE, 24
 VERR_SIGN, 23
 VERR_TIME, 23
 VERR_TYPE, 23
 VERR_VERIFY, 23
voms_api.h, 21
 check_sig, 22
 data_type, 22
 getVOMSMajorVersionNumber, 24
 getVOMSMinorVersionNumber, 24
 getVOMSPatchVersionNumber, 24
 gss_cred_id_t, 22
 gss_ctx_id_t, 22
 NOGLOBUS, 22
 reurse_type, 22

verify_type, 23
verror_type, 23
vomsdata, 11
 ~vomsdata, 13
 AddTarget, 13
 Contact, 13
 ContactRESTRaw, 14
 ContactRaw, 13, 14
 data, 18
 DefaultData, 14
 error, 18
 ErrorMessage, 14
 Export, 14
 extra_data, 18
 FindByAlias, 14
 FindByVO, 15
 Import, 15
 ListTargets, 15
 LoadCredentials, 15
 LoadSystemContacts, 15
 LoadUserContacts, 15
 Order, 16
 ResetOrder, 16
 ResetTargets, 16
 Retrieve, 16, 17
 RetrieveFromCred, 17
 RetrieveFromCtx, 17
 RetrieveFromProxy, 18
 ServerErrors, 18
 SetLifetime, 18
 SetRetryCount, 18
 SetVerificationTime, 18
 SetVerificationType, 18
 voms, 9
 vomsdata, 12, 13
 workvo, 19
voname
 voms, 11

workvo
 vomsdata, 19